
Setting up DWService to access a remote CAMS computer

By Andy Howell and Dave Samuels

STEP 1 ESTABLISH AN ACCOUNT WITH DWSERVICE.NET


To sign up for a new DWS account, enter your email address and a password

First, in your browser, navigate to: https://dwservice.net




STEP 2 IINSTALL DWAGENT ON THE REMOTE COMPUTER


From the DWService home page, click "Windows" to download the DWAgent installer



Save the DWAgent installer program anywhere on your computer




Double click the installer to open it. Click the radio button to create a new agent



Enter the DWService credentials you created during Step 1. Enter an appropriate name for the agent (whatever you like).

	Enter data to create a	a new agent:	
	DWS user	Enter your DWS user name	
	DWS password	*Enter-your DWS password	
	Agent name	Enter an appropriate identifier	
CAM Where < site	AS- <site name="">-<came e="" e:="" name=""> is something I nera number> is the file CAMS-F</came></site>	ntion for DWService agents as follows: ra list> ike CAMS-FL, CAMS-SA rst camera number for each board. Examples: orestHill-250,258 ick-549,557,565	


To complete the installation process, choose "Install"



Step 3


ADDING THE FIRST AGENT FOR YOUR COMPUTER

Configuring the "first" Agent



Add an Agent for your computer so that you can create shares, which will allow others to connect.

New Agent Dialog




Naming convention:


CAMS-<group>-CAMS-<site> < list of first camera numbers for each board>

Note: A good naming convention will allow local and remote users to manage many computers, agents, and shares with the minimum amount of confusion. Remember to choose names that make sense to the user who will be connecting.

Agent "Install code"



Install DWAgent via Installation Code




Install Code

- Enter Install Code
- Click Finish
- In the Agents tab, click the Refresh icon
- In the Dashboard tab, click the Refresh icon


DWAgent desktop app

- Run the DWAgent desktop app
- Click Configure
- Select: Configure agent
- Click Next
- Click Next



Enter the Installation Code

For Code, enter the Install Code that you wrote down



Click Next


Dashboard

- In the Dashboard, click the Refresh icon
- The Agent should be visible with "Available"

Step 3

CREATE A "SHARE" FOR REMOTE ACCESS

- Log in to DWService.net using your credentials.
- Click the green +" plus icon to add a new share.




Note: In order to be able to create a <u>persistent</u> share that a user can connect to, that user must have an email address registered with dwservice.


You can send a <u>temporary</u> "link" to non-registered users, but those links will not work after rebooting, or restarting DWService, or making changes to any of the DWService configurations




- Assign a name that is meaningful to person you are creating a share for (ask them remote user what share name they prefer or use a naming convention) Optionally, include a description.
- Naming convention for shares:
 CAMS-<network name>/CAMS-<camera list>-<site name>-<user>
 Example: CAMS-SA/CAMS-6000,6020-Bredel-Dave Samuels




In the check box, click "Always"







It's a good practice to add a share for yourself.

After clicking "Accept", DWService will display and Assigned link.
 This link is temporary, since it changes often. For example, if you change anything about the share, such as modifying the description, the link will change. Therefore, ignore this for now and click Close.







Analyze Events tab



DWAgent Monitor





Fully Removing DWService in order to reinstall

- If you need to reinstall DWService, you need to first fully remove it.
- 1. https://speedutilities.com/remove/dwservice.exe.html
- 2. Create a Restore point for Windows.
- 3. Launch Control Panel
- 4. Select Programs and Features
- 5. Locate DWAgent
- 6. Right-click and select Uninstall.
- 1. You might need to remove instances of dwservice and dwagent from the registry.